



1. Access Mobile GSCS

Menu Name : Main

Access : GSFS Mobile / GSCS Mobile

Access Mobile GSCS



Outline

Main Screen

Access by clicking GSCS link in Mobile GSFS Main Screen.



Function

1. Search by Model Number
2. Search by Serial Number or Scan barcode
3. Switch to Product Category List Screen
4. Switch to Favorite List Screen, which selected by the user
5. Most Viewed contents for last 2 years
6. Articles registered during last 3 month



2. Model Detail

Menu Name : Model	Access : GSFS Mobile / GSCS Mobile
Model Detail Screen	



Outline

Search by Model Number and access to the contents of the Model.



Function

1. Type 2 or more digit of the model number and you will see up to 5 matching models.
2. You can see registered contents of selected model in Model Detail Screen.



2. Model Detail

Menu Name : Model	Access : GSFS Mobile / GSCS Mobile
Model Detail Screen	





Function

1. You can add the selected model as one of your Favorites.
2. View Service Bulletins of selected Model.



2. Model Detail

Menu Name : Model	Access : GSFS Mobile / GSCS Mobile
Model Detail Screen	





Function

1. View Error numbers of selected Model.
2. View Test Mode Directions of selected Model.




2. Model Detail

Menu Name : Model	Access : GSFS Mobile / GSCS Mobile
Model Detail Screen	





Function

1. View Exploded View of selected Model, and select location number that you need check the part information.
2. You will see the parts information of selected location.




2. Model Detail

Menu Name : Model	Access : GSFS Mobile / GSCS Mobile
Model Detail Screen	





Function

1. You can download Service Manual.
2. You can cancel the download.




2. Model Detail

Menu Name : Model	Access : GSFS Mobile / GSCS Mobile
Model Detail Screen	





Function

1. View Symptoms of selected Model.
2. You will see the Sub-Symptoms and registered contents of the selected Symptom / Sub-Symptom.




2. Model Detail

Menu Name : Model	Access : GSFS Mobile / GSCS Mobile
Model Detail Screen	



Function

1. View Articles of selected Sub-Symptom.
2. View the contents of selected Articles.




If an internal leak is suspected, begin isolating the system.
-Separate the yoder from the rest of the system, pinch, solder off on the yoder end and then apply pressure to the other (using a Schrader or oroc




2. Model Detail

Menu Name : Model	Access : GSFS Mobile / GSCS Mobile
Model Detail Screen	




When Yoder Loop Leak or Internal Leak is suspected

A good visual inspection of the outside of the unit should be done, paying close attention around the bottom of the refrigerator and freezer compartments for signs of rusting, this is where we usually find the yoder leaking.



If an internal leak is suspected, begin isolating the system.
-Separate the yoder from the rest of the system, pinch, solder off on one end and then apply pressure to the other (using a Schrader or proc





Function

1. You can add the Articles as one of your Favorites.
2. You can feed back the Articles.



3. Category

Menu Name : Category Search	Access : GSFS Mobile / GSCS Mobile
Product Category Screen	




Outline

Access to the Symptom contents by Product.

Function

1. Switch to Product Category List Screen.
2. Select the Product.





3. Category

Menu Name : Category Search

Access : GSFS Mobile / GSCS Mobile

Product Category Screen



Function

1. View Symptoms of selected Product.
2. View Sub-Symptoms of selected Symptom.




3. Category

Menu Name : Category Search

Access : GSFS Mobile / GSCS Mobile


Product Category Screen



Article # 20150157824786
Additional information regarding yoder loop leak
Hit Count 37 Score 0 | 06/17/2016

Article # 20150638931139
Refrigerator: Not cooling entire unit (reciprocating co...
Hit Count 10 Score 0 | 03/09/2018

Article # 20150351030583
Refrigerator: Refrigerant Leak Detection
Hit Count 14 Score 0 | 05/24/2017



Article # 20150638931139 ★
Refrigerator: Not cooling entire unit (reciprocating compressor)
Refrigerator > French Door > Cooling Issues > Not Cooling
Hit Count 10 Score 0 | PATRICIA JONES 03/09/2018

Does (reciprocating) Compressor Run?

↓ No

↓ Yes

[Click here](#)
(go to next section)

Push Test Button (Test Mode 1) Test compressor for proper voltage of 120V. Is voltage correct?	No →	Inspect harness between main PCB and compressor. If harness is loose, reconnect. If harness is good: replace main pcb
------------------------------------------------------------------------------------------------------	------	-----------------------------------------------------------------------------------------------------------------------



Function

1. View Articles of selected Sub-Symptom.
2. View the contents of selected Articles.



4. Favorite

Menu Name : Favorite	Access : GSFS Mobile / GSCS Mobile
Favorite Screen	



Outline

Access to your Favorites and view History.



Function

1. Switch to Favorite List Screen.
2. You can see your Favorites by Service Bulletins, Articles, and Model. And recent search History up to 20 Service Bulletins and Articles.



4. Favorite

Menu Name : Favorite	Access : GSFS Mobile / GSCS Mobile
Favorite Screen	





Function

1. You will see the list of Service Bulletins you've added as your Favorite.
2. You will see the list of Articles you've added as your Favorite.



4. Favorite

Menu Name : Favorite	Access : GSFS Mobile / GSCS Mobile
Favorite Screen	



Function

1. You will see the list of Model you've added as your Favorite.
2. You can see up to 20 Service Bulletins and Articles you've recently clicked.





5. Most Viewed and New Articles

Menu Name : Main

Access : GSFS Mobile / GSCS Mobile

Most Viewed and new articles








Outline

Access to Most Viewed and New Article in Main Screen.


Function

1. Top 5 Most Viewed Article during last 2 years.
2. Articles registered during last 3 months. You will see whole list when you click More button.



6. Serial No scan

Menu Name : Main	Access : GSFS Mobile / GSCS Mobile
Serial Number scan	



Outline

Search Model by Serial number barcode scan.



Function

1. Barcode Scanner App will run when you click Serial No button.
2. After barcode scanned, it will move to Model detail Screen.



6. Serial No scan

Menu Name : Main	Access : GSFS Mobile / GSCS Mobile
Serial Number scan	



Function

1. If barcode scan failed, you can manually type in the serial number.
2. If you moved to Model Detail Screen by Serial No searching, Service Parts History option is available.

